


FIMER Auroravision

API Integration



Enter the AuroraVision UserID and password in the authorization tab

 <https://api.auroravision.net/api/rest/authenticate>

Save

Share

</>

GET

https://api.auroravision.net/api/rest/authenticate

Send

ParamsAuthorization •Headers (10)BodyScriptsSettingsCookies

Auth Type

Basic Auth

The authorization header will be automatically generated when you send the request. Learn more about [Basic Auth](#) authorization.

Heads up! These parameters hold sensitive data. To keep this data secure while working in a collaborative environment, we recommend using variables. Learn more about [variables](#).

Username

Password

BodyCookiesHeadersTest ResultsStatus: 200 OKTime: 486 msSize: 482 BSave as example

PrettyRawPreviewVisualizeText

1

Next enter the API key and run the API

A session token will be generated.

GET

https://api.auroravision.net/api/rest/authenticate

Send

Params

Authorization

Headers (10)

Body

Scripts

Settings

Cookies

Headers

8 hidden

	Key	Value	Description	...	Bulk Edit	Presets
<input checked="" type="checkbox"/>	X-AuroraVision-APIKey					
<input checked="" type="checkbox"/>	Authorization					
	Key	Value	Description			

Body

Cookies

Headers (6)

Test Results

Status: 200 OK

Time: 1629 ms

Size: 482 B

Save as example

Pretty

Raw

Preview

Visualize

JSON

```
1 {
2   "result": "Ne...XBNyOpUCCvL6wT4XRL6tuGaPHPLLtEbJNvgoH23m2Bpq7800DIX7mAo5MielpnC/AMDGTd
   +ZBac7MqN...Zdp0T+jcvTzlc0YUERF7Cqldd+NkU4YChruvV0mXqwAqZm5dKWML00q8oDDpLYayEkUA1XNwnLZ8avSuGo3oof6cf0Pzgpg
   +DWziY4Y9...
3 }
```

Use the session token to poll the required API

HTTP [https://api.auroravision.net/api/rest/v1/portfolio/\[REDACTED\]/plants](https://api.auroravision.net/api/rest/v1/portfolio/[REDACTED]/plants) Save Share

GET ▼ [https://api.auroravision.net/api/rest/v1/portfolio/\[REDACTED\]/info](https://api.auroravision.net/api/rest/v1/portfolio/[REDACTED]/info) Send ▼

Params Authorization **Headers (9)** Body Scripts Settings Cookies

Headers 8 hidden

	Key	Value	Description	...	Bulk Edit	Presets
<input checked="" type="checkbox"/>	X-AuroraVision-Token	NeTBRI5avChYxKc+gZ8oJenvSXBnyOpUCCvL6wT4XR...				
	Key	Value	Description			

Body Cookies Headers (6) Test Results Status: 200 OK Time: 287 ms Size: 314 B Save as example

Pretty Raw Preview Visualize JSON ▼ ≡

```
1 {
2   "result": {
3     "portfolioEntityID": [REDACTED],
4     "portfolioName": "Solar Residence",
5     "portfolioState": "ACTIVE"
6   }
7 }
```